

eDictionary Reader for Pocket PC

Version 4.0

CONTENTS

How the manual is Organized.....	1
Introduction to eDictionary Reader	2
Installation and Uninstallation	2-3
Components	4
eSelector	4
eDictionary Reader	4
Main screen of eDictionary Reader	4
Instruction of functions	5
How to open dictionary	5
Word search	5
Search by pattern	5
Using eSelector	6
Audio Pronunciation	6
Usage of history list	6
Usage of favorites list	6
Tools menu	7
How to change font in eDictionary Reader	7
How to set lexicon's default folder	7
How to use Audio feature with other dictionary	7
How to purchase and register eDictionary Reader	8-9

How the manual is Organized

This manual guide provides detailed information about the different components of the product, its functions as well as instruction of purchase and support.

Symbol	Descriptions
 Text	Special Notes session
 Text	Menu item
{Enter}	Enter button
[Word Entry]	Text-box or List-box
<Tools>	Menu Tools

Introduction to eDictionary Reader

With the launch of Windows Mobile 5.0 operation system and comments of eDictionary users, we have been working urgently to release eDictionary Reader version 4.0 with many improvements such as:

- Fully compatible with [Windows Mobile 5.0](#)
- Support smart text selection for eSelector
- Support Advanced Search
- Support local keyboard for some languages.
- Support favorites
- Speed improvement

Installation for Pocket PC

The required condition: **1 MB** of free space for full version and about 13 MB for trial version (included English-English Lexicon). You need to have MS Active Sync Software on your device.

1. Unzip downloaded file to a folder with a zip tool. The popular unzip program **WinZip** is available at www.winzip.com
2. Run setup and follow instructions

3. When finished, go to **Start Menu>>Program**, here you will see the symbols of **eDictionary**  and **eSelector** 

We recommend storing in the Storage Card when the installation asks to select **Main memory** or **Storage Card**.

 You can copy the CAB file to your device and run the CAB file directly but it will automatically install the software to the main memory.

Uninstallation

To remove the product from your Pocket PC follow the below steps:

1. Go to **Start menu >> Settings**
2. Open **System** and tap on **Remove Programs**
3. You will see **eDictionary Reader** in the list, Select this item and tap on **Remove** button
4. Choose **"Yes"** to confirm removing


Components of eDictionary Reader

The product contains two components:


eSelector: A module to search words in other applications such as *Pocket Internet Explorer, MS Reader, Pocket Word, Mobipocket Reader.*

eDictionary Reader: The main module to enable to search by word, by fixed form, to listen to pronunciation or see related idioms.

Main Screen of eDictionary Reader:



Quickview



Instruction of functions

How to open dictionary:

1. Download lexicons that you want to use from our site or Handango, Pocketgear and other sites
2. Unzip zipped files
3. Each dictionary consists of 2 files: extension LXD and DAT. You have to transfer these 2 files into the Pocket PC and put them in a same folder
4. Run eDictionary and click on "+/- **Dictionary**". Then, the list of lexicons will be on the screen.
5. Tap on "**Add**"  button
6. Show the lexicon file and select the LXD file
7. Save changes and return to main screen by tapping 
8. Now tap on the property button  and select which dictionary you want to use.
9. You can remove a lexicon with the same process.


Word searching: To search a word, you are just to type it in the textbox and tap onto word on the wordlist then you will see the meaning

Searching by pattern: Not only search in a popular method, **eDictionary Reader** support searching by pattern as well. For example:

- To search words including "**tion**", you input a pattern of **{*tion*}**
- The "?" mark stands for a character.
- The "*" mark stands for one or many characters.

On the main screen, tap onto  the button in the toolbar, you will goto the screen for Advanced Search.

Anagram Search: This will allow you to search words base on characters in "Rack" and "Board" and sorted by Length or alphabet. On the main screen, a tap on  the button in the toolbar and select  will facilitate the search.



Using eSelector: To find words in other applications such as [MS Reader](#), [Mobipocket Reader](#), [Pocket IE](#), [Pocket Word](#), [Notepad](#).. etc.. **eDictionary Reader** provides you the **eSelector** module with simple manipulations as followings:

- Select a word, then tap onto the button eSelector  you will get meanings at once. You can change into Full-view screen from Quick-view one of eDictionary Reader if tap onto the full-view button  of quick-view screen.

 To [Pocketword](#) and [Pocket IE](#), eSelector enables being attached like a component of the product. It would be very useful if you use these 2 programs regularly.

Audio Pronunciation: eDictionary Reader is the program that can support word pronunciation. After searching, tap onto the button  you will hear the audio pronunciation. At present, we support about **28,000** root words with pronunciation and hope to develop in the next version.

Usage of history list: This is a list of the words previously looked up. At present, the list is limited to **500** words, they are stored automatically and enumerated in the order you used them. To access, go to menu **Show>>History** and the list will be shown.

Using favorites list: To add a word to the favorites list, just tap on the button . To remove a word from the list, merely tap on the button  again. You can show all favorites word from menu **Show>>Favorites**

Menu Tools includes function as followings:

- ◆ Pattern Search To search for a special pattern such as “? *” or Anagram search
- ◆ Select All To select all text in the active window in eDictionary Reader
- ◆ Copy To copy a selected section
- ◆ Preferences... To configure eDictionary Reader. [See further detail at Preferences session](#)
- ◆ About To show copyright and registration of the product.
- ◆ Exit To exit eDictionary Reader

Menu Show includes the following functions:

- ◆ History During every work session the system will automatically save all words looked up to the history list (these will not be saved when you turn the device off)
- ◆ Favorites To show favorites list
- ◆ Text Size To change text-size in meaning view
- ◆ eSelector To active eSelector

[How to change font in eDictionary Reader](#) To change font, please go to **Tools>>Preferences..** then enable “**Option font**” checkbox and then you can choose which font you want to use in the font’s list

[How to set lexicon’s default folder:](#) To set default folder for Lexicons(the system will automatically load all dictionaries in this folder when startup), please go to**Tools>>Preferences..** then choose the folder that you want to set as default folder.

[How to use Audio feature with other dictionary](#)

1. Make sure that you have got Audio English Dictionary (its cost 5 usd)
2. Transfer **voice.dat** and **voice.lxd** to the same folder on your pocket pc
3. Goto **File>>Preferences**.
4. Check "voice enable" check box
5. Point to the folder where you stored **Voice.lxd** and **Voice.dat**
6. Remember to save the changes.
7. And now you can use audio pronunciation with other dictionary as English Dictionary, English Spanish Dictionary etc. When you lookup for a word and you will see working speaker symbol, tap on this symbol and then you will hear the pronunciation of the word.

How to buy and register eDictionary Reader

You can purchase **eDictionary Reader** at:

1. www.ppclink.com
2. Handango.com
3. Pocketgear.com
4. Mobile2day.de

In these addresses, we have a same price. Anyway, the price will be a pretty alternative sometimes in each address due to sales promotion.

 If you purchase direct from our website at ppclink.com, you will receive an account by which you would download upgrade versions, submit questions or get our direct support as well.

☐ When you purchase direct from our website, you will get an email of **2CheckOut** to confirm your order and we will send you an account by which you can login our website at: <http://www.ppclink.com/?ppclink=member> to get the **Serial Key**. In case of loss, you can re-login and take the serial key. After getting the registration key, Follow these steps to unlock the product:

1. Run eDictionary Reader
2. Go to Menu **Tools -> About**

3. Enter the name and number exactly as in the order tap on Register button.

After successfully enter registration, write the name and number down and keep it in a safe place. You will need the registration key if you are going to reinstall the software in a new device or after your device is hard-reset. . You can get support information or frequently asked questions at http://ppclink.com/?ppclink=product&do=view&id=22&type=product_faq

If you have any issues, please contact us at:

PPCLINK Support support@ppclink.com

License license@ppclink.com

Online support <http://www.ppclink.com/?ppclink=member>

▣ If you purchase at **Handango** or **PocketGear**, you will receive serial and support from them as well. If you get trouble with these site, please contact:

Handango

Online form: <http://www.handango.com/CSsupport.jsp>

Support email: support@handango.com

Pocketgear:

Online form: <http://www.pocketgear.com/contact.asp>

Support email: support@pocketgear.com